

# Inbound Calls

## Auto Attendant (IVR)

### Auto Attendant IVR

Auto Attendant is your virtual receptionist or IVR, that can greet all inbound calls and direct the caller to the department they require. Example: "Welcome to Our Company if you would like to speak to our customer service team press one, accounts press two...."

With Auto Attendant you can:

- Use time schedules to set when your auto attendant is to be active.
- Set a time for response time, before the Auto Attend message replays.
- Choose how many times to replay Auto Attend message, before the calls get directed to the number Auto Attend is set up on.
- Create a greeting only. Limit the Auto Attendant to a greeting message then use the call forward to route the call once the greeting message completes (see simple **Quick Guide - Greeting Only**).

## Quick Guide

### Setting up Auto Attendant with Call Forwarding

1. Log in to your <https://now.tel2.co.uk> > select number you wish to set up Auto Attendant.
2. Select **Inbound Calls > Auto Attendant**.
3. Either record your Auto Attendant message or upload your recording in Media.
4. Set your time you want your Auto Attendant play.
5. Select the numbers you want to use for in your Auto Attendant. **Note:** If you are planning on using extension think about creating cohesion with your extension dialing numbers.
6. Click **Save settings** to update your settings (see Quick Guide - Simple Queue below).

## Quick Guide

# Inbound Calls

## Setting up Auto Attendant - Greeting Only

1. Log in to CloudPBX > select number you wish to set up Auto Attendant
2. Select **Cloud PBX** > **Inbound Calls** > **Auto Attendant**.
3. Set your Target numbers and time schedules.
4. Set Seconds to Wait: 2 Times to play: 1 (see screen shot below)
5. DO NOT set **forwarding numbers** within the AutoAttendant (see screen shot below)
6. Set Call Forward: Use Forwarding and trunking to route the call to the required function (eg Queue or SimRing)
7. Click **Save settings** to update your settings.

### Inbound Calls

#### Auto Attendant

Create your own auto attendant prompts for callers

[Click here to record your Auto Attendant message now.](#)

☒ Enable auto attendant feature on this line

Play your auto-attendant menu: At all times

2 seconds to wait for a response from caller after playing auto-attendant message

1 times to play your auto-attendant message

☒ Connect to your number as normal on timeout or if an invalid digit is entered (i.e. no forwarding number is setup for that digit)

Digit '1' forwarding number:

Digit '2' forwarding number:

Digit '3' forwarding number:

Digit '4' forwarding number:

# Inbound Calls

See also Call Queuing our Auto Attendant solution knowledge base.

Unique solution ID: #1017

Author: Support

Last update: 2016-05-28 03:42